

**SETUP** ADVANCED MAINTENANCE STATUS HELP

Wizard  
Local Network  
**Internet Setup**  
Wireless Setup  
Time and Date

**CHANNEL CONFIGURATION**  
This page is used to configure the parameters for the channel operation modes of your ADSL Modem/Router. Note: When connect type of PPPoE and PPPoA only is "Manual", the "Connect" and "Disconnect" button will be enable.

**WAN PHYSICAL TYPE**  
WAN Physical Type:  DSL WAN  Ethernet WAN

**DEFAULT ROUTE SELECTION**  
Default Route Selection:  Auto  Specified

**CHANNEL CONFIGURATION**  
VPI:  VCI:  Encapsulation:  LLC  VC-Mux  
Channel Mode:  Enable NAPT:  Enable IGMP:   
VLAN:  Disable  Enable VLAN ID(1-4095):   
IP Protocol:   
PPP Settings: User Name:  Password:   
Type:  Idle Time (min):   
WAN IP Settings: Type:  Fixed IP  DHCP  
Local IP Address:  Remote IP Address:   
Netmask:   
Channel Mode:  Enable NAPT:  Enable IGMP:   
VLAN:  Disable  Enable VLAN ID(1-4095):   
PPP Settings: User Name:  Password:   
Type:  Idle Time (min):   
WAN IP Settings: Type:  Fixed IP  DHCP  
Local IP Address:  Remote IP Address:   
Netmask:   
Default Routes:  Disable  Enable  Auto  
Unnumbered:   
Connect Disconnect **Add** Modify Delete Undo Refresh

**CURRENT WAN TABLE:**

Select	Inf	Mode	VPI	VCI	Encap	NAPT	IGMP	DRou	IP A	Rem	Netm	User	Statu	Edit
<input type="checkbox"/>	pppe	PPPoE	0	32	LLC	On	Off	On	10.1 13.6 5.99	82.1 37.2 00.3	255. 255. 255		Up	
<input type="checkbox"/>	pppe	PPPoE	0	32	LLC	On	Off	Off	10.1 13.6 5.99	82.1 37.2 00.3	255. 255. 255		Up	

**Helpful Hints...**  
When configuring the router to access the Internet, be sure to choose the correct [connection type](#) from the list below.  
Please take care when entering your [username](#) and [password](#) as these are case sensitive. The majority of connection issues are caused by incorrect [username](#) or [password](#) combinations.  
Note: Be sure to restart the router for the new Internet Setting to take effect.

Internet Setting to take effect.  
More...

DL-282 // SETUP ADVANCED MAINTENANCE STATUS HELP

Wizard  
Local Network  
Internet Setup  
Wireless Setup  
Time and Date

**PPP INTERFACE - MODIFY**  
This page is used for advanced PPP interface configuration.

**PPP INTERFACE**

Protocol: PPPoE  
 ATM VCC: 0/32  
 Login Name:  *اتصل بمزود الانترنت الخاص بك للحصول على اسم المستخدم وكلمة المرور*  
 Password:  \*\*\*\*\*  
 Authentication Method: AUTO  
 Connection Type: Continuous  
 Idle Time (s): 0  
 Bridge:  Bridged Ethernet (Transparent Bridging)  
 Bridged PPPoE (Inherits Bridged Ethernet)  
 Double Bridge  
 AC Name:   
 Service Name:   
 MTU (1-1500): 1492  
 Static IP:   
 Source Mac address: 88:AE:1D:FD:7E:67 (a:00:02:86:71:05:00)  
 MACCLONE

Apply Changes Return Undo

**BROADBAND**

DL-282 // SETUP **ADVANCED** MAINTENANCE STATUS HELP

Advanced Wireless  
Access Control List  
Port Triggering  
Port Forwarding  
DMZ  
Parent Control  
Filtering Options  
DOS Settings  
DNS  
Dynamic DNS  
Network Tools  
**Routing**  
NAT

**ROUTING CONFIGURATION**  
This page is used to configure the routing information. Here you can add/delete IP routes.

**HOST**

Enable  *رقم القناة لازم يكون نفس رقم القناة التي تم انشاء اتصال ip-tv عليها*  
 Destination: 10.237.239.0  
 Subnet Mask: 255.255.255.0  
 Next Hop:   
 Metric: 1  
 Interface:  *ppoe2*

Add Route Update Delete Selected Show Routes

**STATIC ROUTE TABLE**

Select	State	Destination	Subnet Mask	NextHop	Metric	IF

**BROADBAND**